


Creating a new layout ticket using the Copy Prinergy Job option

If you are using the **PLA System Level Rule-Versatile Layout Home** rule set, you can copy an existing Prinergy Workflow job and use it to create a new job. Bleeds are retained and it is possible to replace existing artwork.

Important: It is not possible to use the **Copy Prinergy Job** option if you locked the artwork in the original layout. If you need to copy a job with locked artworks, open the original layout and unlock the artwork prior to using this feature in PLA.

Note: A complete change of a job name in Prinergy is not supported with the **Copy Prinergy Job** option. However, if you add a prefix to the job name for identifying the print site location after it is sent from PLA, it requires the use of the `PrinergyJobNamePrefix.properties` file to allow PLA to find the Prinergy Job to Copy. This file is found at `\\<servername>\Program Files (x86)\Kodak\LayoutAutomation\server\WEB-INF\classes`. It is necessary to add each site location name and its associated prefix to this file following the syntax `SampleName=SN`. If you are using PLA Distributed Processing, please ensure that the `PrinergyJobNamePrefix.properties` file on the secondary server(s) contains the same information as the one on the main PLA server.

1. On the **Status** tab, click **Copy Prinergy Job**.
The Copy a Prinergy Job dialog box opens.
2. In the **Input a new Prinergy job name** box, type a new job name.
3. Ensure that the Prinergy Job Home URL indicates the path where the Job is stored. For example: `\\<servername>\AraxiVolume_<servername>_J\Jobs`.
Important: This path can be adjusted as needed to point to different job homes for each new Copy Job.
4. To copy a job, select it in the **Pick up a Prinergy job** list.
5. Choose a JT or PJTF file. If multiple layouts exist, confirm the selection.
6. Confirm the layout ticket:
Note: This should indicate the ticket that was originally used to create the job if PLA originally created it.
 - On an Apple Macintosh computer: **Select a Layout Ticket Type** list
 - On a Windows OS-based computer: **Layout Ticket to use for new job** list
7. (Optional) To keep the existing artwork, select the **Keep artwork in new Prinergy job** box.
8. Click **Do Copy**.
9. In the layout ticket window that appears, complete the remaining boxes in the dialog box. Required data is indicated by 
Tip: For boxes that accept artwork or dies, you can:
 - Drag the artwork or die file from the Workshop user interface or your file management software to the box.
 - Select **Add InSite Files** to add artwork or dies from the Kodak InSite Creative Workflow. The file must be accessible from the Prinergy Workflow primary server.
 - **Note:** The PLA software does not automatically upload local files from the Client to the Prinergy Workflow primary server.
10. Click **Validate**.
If the layout passes validation, you see the message: `Information: Validation`

completed successfully.

Otherwise, resolve the issues indicated in the validation warning or validation error message.

11. Perform one of the following actions:

- Click **Send to Prinergy**. A job that contains the copied layout is created in Workshop.
- To save the layout data without sending it to Prinergy Workflow, click **Save to File**.