

Running the InSite Configuration Utility (ICU)

Note: If the Prinergy Workflow software was upgraded—for example, you completed a Prinergy upgrade, rehost, or migration—run the InSite Configuration Utility (ICU) before you upgrade the InSite server.

1. On the Prepress Portal or PressProof server, open a commandprompt window.
2. Type ICU and then press Enter.
The **InSite** and **w3svc** services stop, and the ICU wizard appears.
3. Click **Next**.
4. On the Prinergy primary server Info screen, confirm the name and IP address of the primary server. If incorrect, type the correct server name and/or IP address.
5. Click **Next** until the Email Relay Server screen appears.
6. On the Email Relay Server screen:
 - If you are using an email relay server other than Microsoft email relay server:
 - a. Check **Default Email Service** checkbox.
 - b. Enter the IP address or a Fully Qualified Domain Name (FQDN) of the e-mail relay server
 - If you are using Authenticated SMTP through Office 365:
 - a. Check **Authenticated SMTP** checkbox.
 - b. Enter the Microsoft email relay server name. It could be smtp.office365.com, but it could also be another server, for example, [yourdomain.mail.protection.outlook.com](mailto:<yourdomain>.mail.protection.outlook.com) might be your mailserver. Please consult your Microsoft 365 Admin Center for more information.
 - c. In the **Email Account** field, enter one email address in your Microsoft 365 tenant authorized to send mail.
 - d. In the **Password** field, enter the password for the Email Account.
 - e. In the **HTTP Proxy** field, if your site is using a proxy for your servers to access the World Wide Web, enter the proxy's URL. Consult your IT department to see if a proxy is being used.
 - f. In the **HTTP Proxy Port** field, enter the port number that the HTTP proxy will accept requests on. Consult your IT department to obtain the information.
 - If you are using OAuth2:

Important: In order to select this option, you need to complete the prerequisites for OAuth2 integration in article KA28816 on Customer Portal

 - a. Check **OAuth2 (Office 365 only)** checkbox.
 - b. In the **Tenant Id** field, enter Tenant Id.
 - c. In the **From Email Account** field, enter the email address that you want to use as the sender's email address
Note: The email address must already exist in your tenant.
 - d. In the **Client Id** field, enter Client Id.
 - e. In the **Client Secret** field, enter Client Secret.
 - f. In the **HTTP Proxy** field, if your site is using a proxy for your servers to access the World Wide Web, enter the proxy's URL. Consult your IT department to see if a proxy is being used.
 - g. In the **HTTP Proxy Port** field, enter the port number that the HTTP proxy will accept requests on. Consult your IT department to obtain the information.

7. Click **Next** until the Configuration Summary screen appears.
8. Click **Apply**.
9. When configuration is finished, click **Next**, and then click **Close**.
10. Click **Close**.