

# Ports required

The following ports are used by Prinergy, and need to be open for Prinergy to work:

Port	Protocol	Process
80	TCP	IIS Server, Setup, Track, *Automatic License Renewal
443*		HTTPS (*required for automatic license renewal functionality)
445	TCP	SMB
548	TCP	AFP (only required if clients use AFP to mount job volumes)
1024 - 9000	TCP	Daemons, JTPs, UADM, Workshop
1521, 2481	TCP	Oracle
30208, 30209	TCP	PrinterJTP to Veris
49100 - 49102	TCP	Orbacus connection for daemons
49108, 58888	TCP	Link
37000, 37001	TCP	DiagView daemon, DiagView
50010	UDP	Floating License Manager
56765	TCP	Floating License Manager
37100, 37101	TCP	Dashboard components
61233, 61234, 61235, 18804	TCP	RBA components
18005, 18080	TCP	Prinergy Layout Automation
37102, 37150 - 37250, 61237	TCP	Digital Print
52001	TCP	Colorflow
37002	UDP	Plocator
32000-32003, 31000-31003, 52002, 8082-8085, 8091	TCP	Help system

**Note:** AFP port information is given for informational purposes and legacy configurations only. AFP is not qualified with Prinergy Workflow 8.0.

**The Built-in Windows Firewall is not supported**

The software firewall that ships with Windows 2008 and Windows 2012 is not supported on a Prinerger Connect /Direct/Powerpack server.

Aside from the list of static ports listed above, Prinerger Connect/Direct/Powerpack uses many ephemeral (temporary) TCP/IP ports over a very wide range. Activating the built-in Windows firewall will cause unpredictable system behavior.

Any firewalling requirements must be met with an external device. Choices include a hardware firewall, software firewall running on another (non-Prinerger) server, or a firewall appliance in a virtual environment. Placement of the firewall in your network infrastructure is important, as Prinerger requires a large range of ports to be opened between primary and secondary servers and Workshop clients.

Information about the firewall requirements of InSite Prepress Portal, InSite Creative Workflow, and other Kodak portal products can be found in the respective products' documentation.

### **Additional Firewall considerations**

If there is a firewall between the Prinerger servers and the Workshop clients, it is critical that the firewall does not close idle connections after some arbitrary time period. If it does, this could result in lags or stalls in Workshop when it is forced to re-establish its connections to the server. Instead, the firewall should be configured to only close the connection if it is determined to be dead by probing to the end hosts to determine the validity of the connection. This feature is known as 'Dead Connection Detection' on Cisco firewalls. If such a feature does not exist on your chosen firewall then the idle timeout should be set to a period equal to a typical production shift and operators should be warned that Workshop may stall for up to a couple of minutes when they return to it if it has been left running but idle for a longer period.

### **Local-Link IPv4**

Subnet IP range 169.254.x.x is reserved within the IPv4 specification for Local-Link self-assigned IP addresses and is not operationally compatible with Prinerger Workflow server software.

See [IETF.org](https://tools.ietf.org/html/rfc3927) article rfc3927 - <https://tools.ietf.org/html/rfc3927>