

Setting up Kodak Distiller Assistant

Download and install the Kodak Distiller Assistant.

The Kodak Distiller Assistant supports both Mac and Windows clients. This software is compatible with Adobe Acrobat 4.0 (or later), for Windows 98, Windows XP, Windows NT, and Windows 2000.

The Kodak Distiller Assistant replaces the older start-up files PrinergerForDistiller and Synapse Distiller Startup. If applicable, delete these files in your Startup folder when you upgrade.

1. Go to <http://partnerplace.kodak.com> and go to article [67437](#) and download the the zipped file of the Distiller Assistant.
2. Extract and copy the CreoDistillerAssistant file to the Distiller Startup folder.
 - If you are using Distiller 6, the folder location is C:\Documents and Settings\All Users\Documents\Adobe PDF 6.0\Startup on a Windows-based computer, or /users/shared/Adobe PDF 6.0/startup on a Mac computer.
 - If you are using Distiller 7, the folder location is C:\Documents and Settings\All Users\Documents\Adobe PDF 7.0\Startup on a Windows-based computer, or /users/shared/Adobe PDF 7.0/startup on a Mac.
 - If you are using Distiller 8, the folder location is C:\Documents and Settings\All Users\Application Data\Adobe\Adobe PDF\Distiller\Startup on a Windows-based computer , or /Library/Application Support/Adobe/Adobe PDF/Distiller /Startup on a Mac.
3. If applicable, delete any file named Example.ps from the Distiller Startup folder because this file can interfere with the proper operation of the Kodak Distiller Assistant.
4. Copy the Creo PDF Pages.joboptions file to the Distiller Settings folder.
 - If you are using Distiller 6, the folder location is C:\Documents and Settings\All Users\Documents\Adobe PDF 6.0\Settings on a Windows-based computer , or /users/shared/Adobe PDF 6.0/settings on a Mac.
 - If you are using Distiller 7, the folder location is C:\Documents and Settings\All Users\Documents\Adobe PDF 7.0\Settings on a Windows-based computer , or /users/shared/Adobe PDF 7.0/settings on a Mac.
 - If you are using Distiller 8, the folder location is C:\Documents and Settings\All Users\Application Data\Adobe\Adobe PDF\Distiller\Settings on a Windows-based computer , or /Library/Application Support/Adobe/Adobe PDF/Distiller /Settings on a Mac.
5. You can delete the Prinerger Pages.joboptions file, but this is not required.
6. Start Acrobat Distiller.
7. From the Distiller Job Options menu, select **Creo PDF Pages**.

Although these options are the recommended settings for Prinerger input files, they are not required for the Kodak Distiller Assistant to function properly.

The Kodak Distiller Assistant is always active and automatically does its job by intercepting and improving PostScript codes.