

Retrieving a permanent license key for your Prinergy installation

When your Prinergy system is first installed, the system is registered and the Prinergy license is entered in Prinergy Administrator on your behalf. At any time after the system is installed, you can use PLAS to retrieve your existing permanent license key. If you are entitled to any new Prinergy features that became available between the time that you ordered your Prinergy system and the time that the system was installed at your site, PLAS will provide you with a new permanent license key to enable the new features.

The new license contains all of your Prinergy licensed options and replaces your existing license.

1. In PLAS, click **View registered products**.
2. Select your site, select the Prinergy installation for which you want to retrieve the license key, and click **Continue**.
3. Click **Retrieve existing license**.
Your permanent Prinergy license key is displayed. If applicable, it includes any new Prinergy options to which you are entitled.
4. Click **Download the license key** to download the key in an .xml file.
5. In Prinergy Administrator, replace the existing Prinergy license with the new license:
 - a. Save a copy of your existing Prinergy license. See [Saving license key information](#).
 - b. Remove your existing license. See [Removing a license key](#).
 - c. Enter your new license. See [Entering a license key](#).

Prinergy Workflow software-based licenses can be retrieved in Online (automatic) and Offline (manual) methods as detailed below.

Online (automatic) license key retrieval

Requirements

- Access to the internet
If you want to use the license retrieve feature but your Prinergy system is behind a firewall that prevents outgoing connections from the server, allow connections to <https://plas.kodak.com/webservicesite/soap/CustomerLicenseWebService.asmx>
Enable TCP ports 80 (HTTP) and 443 (HTTPS). Enable SSL connections with port 443.
- A Kodak Customer Community user ID

When installing the Prinergy Workflow software on your primary server, the installer will display a licensing dialog box, already populated with your server's unique system ID.

1. In the **License ID** box, enter your license ID.
Note: Your License ID is the same as your Prinergy Workflow serial number which takes the form YCxxxxx or YCxxxxx-xx.

- If you already have a Kodak Customer Community account, log on to at <https://customer.kodak.com> Navigate to **Plas > Service & Support > Product Registration and License Activation > View registered products** and select your site. A list of registered products will be shown, including the serial number for your Prinergy Workflow system (generally, in the form YCxxxxxx, YCxxxxxx-xx, or YCxxxxxx-xxx).
 - If you do not have a Kodak Customer Community account, but you have a support plan that entitles you to the Prinergy upgrade, you can register on Kodak Customer Community at <https://customer.kodak.com>. Then log on to Kodak Customer Community at <https://customer.kodak.com>. Navigate to **PLAS > Service & Support > Product Registration and License Activation > View registered products** and select your site. A list of registered products will be shown, including the serial number for your Prinergy Workflow system (generally, in the form YCxxxxxx, YCxxxxxx-xx, or YCxxxxxx-xxx).
2. In the Kodak Customer Community **username** box, enter your Kodak Customer Community user ID.
 3. Click **License Key**.
 4. Click **Retrieve License**. Your new license key is automatically retrieved from PLAS and your Prinergy server will continue to contact the KODAK Product License and Activation System (PLAS) in the background on a regular basis to keep your system licenses up to date.

Note: If you are unable to retrieve a license automatically, but have met the requirements above, it is possible your system may not be configured to work with certificates correctly. In these cases, the issue may be able to be resolved by updating Internet Explorer to the latest version and/or applying current updates to your Windows server.

Offline (manual) license key retrieval

Requirements

- A workstation or server, other than the Prinergy Workflow primary server that has Internet access
- A Kodak Customer Community user ID

If your Prinergy server cannot access PLAS or does not have access to the Internet, you will need to download a license file from a workstation or server that has Internet access. When the Prinergy Workflow installer detects that it is unable to contact PLAS, it will present you with a Software License dialog box that provides an opportunity to save an XML file containing the necessary information to generate a license.

1. From the Prinergy ESetup Software License dialog box, click **Browse** to select a location for the XML request file, and click **Save** to save the file.
2. Copy the XML file to another workstation that can access the PLAS server on the Internet.
3. From that workstation, connect to <https://plas.kodak.com/FileUpload> and use the tools on that page to upload the XML file. PLAS will generate a new XML file that you can use to license your Prinergy server.
4. Download and copy the new XML file to the Prinergy server.

5. Submit that file to Prinergy by clicking the **Load license key from file (manual/trial)** button, then **Browse** to locate a license file, and then **Read File**. Multiple licenses may appear in the licensing dialog box.
6. Select the license you want to apply to the server, click **Apply** to install the license, then proceed with the upgrade installation.

Automatic License Renewal

If your Prinergy Workflow server has Internet access as described above, purchased licenses will be automatically renewed on a regular basis. If the Prinergy Workflow server is unable to reach PLAS for extended periods of time, it will begin notifying the system administrator two weeks before the base license is set to expire. If your Internet connection cannot be restored within two weeks, retrieve an updated license file to renew the base license using the manual method.

Important Notes:

- The server should have access to the following URLs <https://plas.kodak.com> and <https://customer.kodak.com>
- The license manager utilizes ports 80 and 443
- The licensing server is located on Kodak infrastructure
- Kodak utilizes Microsoft front door to facilitate worldwide content distribution, load balancing and access to the server.
- If security is a concern, you can whitelist the URLs (but not the IP addresses) as the IP addresses are dynamic and allocated by Microsoft front door.
- Kodak cannot provide a specific IP range that is going to be utilized by the licensing server.