

# Undoing or redoing previous adjustments

You can undo or redo adjustments made to a curve or DeviceLink.

When you make an adjustment to a simulation, a conversion, or a curve, you can undo individual changes until you click **Apply**. After you click **Apply**, you can only undo a group of adjustments. You can use the **History** dialog box to view details on a list of the previous adjustments.

1. Open the **Adjustment** dialog box for a simulation, conversion, or curve.
2. Click **History...** to view the list of adjustments.
3. Select the **Edit** menu. The last adjustment action in the list is automatically selected for **Undo**. The last action undone is automatically selected for **Redo**. Choose **Undo <last action>** or **Redo <last action>**. You can only undo adjustments sequentially in the reverse order in which they were made.