

Creating your own color library

1. From the **Configure** menu, select **Color Definitions**.
2. In the Color Database Editor dialog box, **Color Libraries** list, select **User Libraries**.
3. Click the **Add** button.
4. In the New Color Library dialog box, **Library Name** box, type a name for your color library.
5. In the **Library Color Space** section, select a color space option: **CMYK** or ***L*a*b*{}**.
6. Click **Add**.
7. In the **Colors** section, click **Add**.
8. In the New Color dialog box, in the **Color name** box, type the color name.
9. Click **Add**.
10. In the **Alternate Color** box, enter the color recipe using either the value slide bar or by typing the values in the color boxes: **C,M,Y, K**, or **L, a, b**.
11. Click **Apply**.

The color recipe is saved and in the **Colors** list a color swatch appears beside the color name.