

Restarting Prinergy Evo

You can only restart Prinergy Evo software while Prinergy Evo is running.

1. Right-click the **Prinergy Evo Administrator** icon on the system tray.
2. Click **Open** to open the Prinergy Evo Administrator dialog box.
3. In the **System** tab, click **Restart** in order to automatically start Prinergy Evo software.
4. In the Prinergy Evo Shutdown-Restarting dialog box, set the options as required.
5. To stop processing immediately, in the Restart Prinergy Evo dialog box, in the **Choose how to restart Prinergy Evo** list, select the option that determines the state of the Prinergy Evo system after restart:
 - **Finish current processing before stopping Prinergy Evo**
Prinergy Evo software waits until the current file has finished processing before stopping the Prinergy Evo Server software.
 - **Halt processing immediately (may be resumed later)**
Newly submitted processes are not initiated until after restart.
6. Click **Restart Now**.
Prinergy Evo normally takes at least one minute to stop and restart.
For emergencies where the system appears to be indefinitely stopped, click **Force Quit**.
7. Click **Done**.