

Creating multiple output versions for the SCO

In a color setup, if you want to create an alternate SCO conversion method for the PCO, rather than creating a new color setup, you can create a new output version for the same SCO. You can also copy an existing conversion and then make adjustments. You can [select one version as the default color output for Prinerger](#). In Prinerger, you can also choose the desired version from a dropdown list in Prinerger Refine Process Templates.

1. Click the **Color Setups** tab, and then click the desired color setup from the list to show it in the viewer window.
2. In the **Color Setups** viewer, click the **Conversion** icon  between the PCO and SCO.
3. To create a new version:
 - a. In the **Conversion Edit** dialog box, click the **Edit** icon  next to the **Output Version** drop-down list.
 - b. Click the **Add** button .
 - c. [Define a new conversion version for the SCO.](#)
4. To copy the existing version with adjustments:
 - a. From the **Output Version** list, select a desired output version that you want to copy.
 - b. Click **Duplicate**.
 - c. Enter a version name.
 - d. Click **Copy conversion with adjustments**.
 - e. To adjust the copied conversion, click the **Conversion** icon  and select the copied version from the **Output Version** list.
 - f. Make your adjustments.