

# **\_evaluate a DeviceLink**

Do the following:

- To evaluate tint values through the DeviceLink:
  1. In the **Input Tints** panel, select the **Tint Value Range** of input tint values you wish to evaluate.
  2. Double-click in the first cell of the **Input Tints** table.
  3. Type a Cyan input tint value, or a Red input tint value for an RGB-input DeviceLink.
  4. <tab> to advance and enter a Magenta (or Green) input tint value.
  5. Repeat for other input tint values.
  6. Repeat to enter another set of input tint values.
  7. Terminate input tint entry with <enter>.
  8. In the **Output Tints** panel:
    - select the desired **Tint Value Range** of evaluated output tint values.
    - enter the desired **Tint Precision** of evaluated output tint values.
  9. Click **Evaluate** below the Input Tints table.
- To copy, paste and evaluate multiple input tints:
  1. Select an array of input values in a spreadsheet or tab-delimited text file.
  2. Copy.
  3. Click in the ColorFlow Evaluate **Input Tints** table.
  4. Select all.
  5. Paste.
  6. Click **Evaluate**.
- To copy output tints for use by another application:
  1. Click in the **Output Tints** table.
  2. Select all.
  3. Copy.
- To combine the above two operations:
  1. Select an array of input values in a spreadsheet or tab-delimited text file.
  2. Copy.
  3. In ColorFlow Evaluate, click **Paste - Evaluate - Copy**.