

Duplicating a color setup

WARNING

When you duplicate a color setup, the new color setup uses the **same device conditions** as the original color setup. If you **change the device curves**, color response or device condition profile in the duplicate color setup, they will **also change** in the original color setup.

You should therefore duplicate a color setup only if you wish to align the same PCO device condition to two different simulation targets, or with different simulation definitions. Editing device curves in either color setup will change the device curves in the other color setup.

Do not duplicate a color setup to experiment with device curves, measurements or a device condition profile.

To duplicate a color setup:

1. In the **Color Setups** list, select the color setup that you want to duplicate.
2. Click the **Duplicate** button at the bottom of the **Color Setups** list table.
The color setup you duplicated appears in the **Color Setups** list as ***color setup copy***.
3. To change the name of the new color setup, double-click its name in the **Color Setups** list, and type a new name.