

Exporting a DeviceLink

You can export a DeviceLink from ColorFlow to use it in other software. In the Workflow and Pro Workflow editions of ColorFlow, you do not need to export the DeviceLink in order to use them in Prinergy.

1. In a color setup, perform one of the following actions:
 - To export a simulation DeviceLink, click the border of the PCO.
 - To export a conversion DeviceLink, click anywhere in the conversion connection area.
2. Select **Export > DeviceLink Profile**.
3. In the **Save DeviceLink Profile** dialog box, browse to the location where you want to save the DeviceLink.
4. Use the default file name for the DeviceLink or type a new file name and click Save.
The device profile is saved as an `.icc` file.