


Objective 2—Import a die and artwork, and position on the substrate

1. Perform one of the following actions:
 - From the **File** menu, select **Import > Folder**.
 - In the Pandora toolbar, click the **Import Folder** icon .
2. In the Import Folder dialog box, navigate to the location where you are storing the sample activity files.
3. Select the `Bleed Samples` folder, and click **Open**.
The artwork and die are added to the **Content** tab, and the die appears on the layout.
4. Click outside the die to deselect it.
5. Using the **Selection Tool**, press Shift and select die stations number 1 and 3.
6. Drag the `Green Box.pdf` file to the selected die stations.
7. Click outside the die to deselect it.
8. Press shift and select die stations number 2 and 4.
9. Drag the `Red Box.pdf` file to the selected die stations.
10. Click outside the die to deselect it.

