

Viewing the history of a color control element

You can view a list of adjustments that have been made to a particular color control element.

1. Open the **Adjustment** dialog box for a simulation, conversion, device profile, or device curve and click the **History...** button.
 - a. Or from the **View** menu, click **History**.
2. Perform one of the following actions:
 - To view adjustments that were made at one time, expand the appropriate **Adjustments to <element type> on <date>** list entry.
 - To view recent adjustments that have not yet been committed, expand the **Uncommitted** list entry
 - A list of adjustments appears under the expanded entry. When you first make an adjustment to a color control element, each adjustment detail appears in the **Unapplied** entry list in the **History** window. These details include edit point selection, range selection, color changes, tint changes, and other settings, depending on the color control element and adjustment mode. When you click **Apply** in the adjustment dialog box, the unapplied adjustment details are combined into a single adjustment event and are listed in the **<element type> Adjustment on <date and time>** list entry in history.
3. If you close the adjustment dialog box before you apply your adjustments, adjustments are discarded and disappear from the history list. Any adjustments you have applied remain in the history list, even after you restart ColorFlow.