

Restarting Prinerger Evo

You can only restart Prinerger Evo software while Prinerger Evo is running.

1. Right-click the **Prinerger Evo Administrator** icon on the system tray.
2. Click **Open** to open the Prinerger Evo Administrator dialog box.
3. In the **System** tab, click **Restart** in order to automatically start Prinerger Evo software.
4. In the Prinerger Evo Shutdown-Restarting dialog box, set the options as required.
5. To stop processing immediately, in the Restart Prinerger Evo dialog box, in the **Choose how to restart Prinerger Evo** list, select the option that determines the state of the Prinerger Evo system after restart:
 - **Finish current processing before stopping Prinerger Evo**
Prinerger Evo software waits until the current file has finished processing before stopping the Prinerger Evo Server software.
 - **Halt processing immediately (may be resumed later)**
Newly submitted processes are not initiated until after restart.
6. Click **Restart Now**.
Prinerger Evo normally takes at least one minute to stop and restart.
For emergencies where the system appears to be indefinitely stopped, click **Force Quit**.
7. Click **Done**.