

Installing ColorFlow client software

ColorFlow software works with Prinergy with the client/server model. The ColorFlow server software is installed on the Prinergy server and the ColorFlow client software can be installed on one or more Mac or Windows workstations.

For Windows, Microsoft .NET framework 3.5 is required for installing the ColorFlow client software. The user account must have administrator privileges. For a complete list of specifications for the client workstation, see the *Supported client workstations* section in the Prinergy release notes.

1. Locate the shared **ColorFlowInstaller** folder on the Prinergy system.
2. Run the appropriate ColorFlow software installer for your computer's operating system.
Perform one of the following actions:
 - For Mac OS X, open the **MacOSX** folder and run `ColorFlow.dmg`.
 - For Windows, open the **PC** folder and run `ColorFlowSetup.exe`.
3. Follow the installation prompts.

ColorFlow provides device drivers for the supported measurement devices. If you connect a measurement device to a Windows-based workstation running the ColorFlow client software, the Windows New Hardware Wizard should appear. If the wizard cannot automatically find the drivers, they can be found at `c:\Program Files\Kodak\colorflow\drivers`. When you install a new version, ColorFlow automatically migrates your data from the previous version.