


# Changing the simulation target or method

You can recalculate the curves and/or DeviceLinks that ColorFlow has generated for a simulation.

1. In the **Color Setups** viewer, in the PCO, click the **Simulation** icon .
2. Click **Redefine**.
3. [Select a new simulation target and simulation method](#).
4. If you only want to regenerate the DeviceLink, or if you don't want to update all the spot ink simulation curve channels, do the following:
  - a. Click **Details**.
  - b. To only regenerate the DeviceLink, select the **Process Ink Simulation** check box, and then click the **Simulation DeviceLink Only**.
  - c. In the **Spot Ink Simulation Update** list table, select or clear the spot ink channels that you want or don't want to update.
  - d. Click **OK**.