


# Evaluating an input conversion DeviceLink

You can evaluate input tints through a color input conversion DeviceLink.

1. In the **color setup viewer**, click the **Conversion** icon  between the color input and the PCO.
2. From the **Input Version** list, select the version for which you want to evaluate the DeviceLink.
3. Click **Evaluate**.
4. Do the following:
  - To evaluate tint values through the DeviceLink:
    - a. In the **Input Tints** panel, select the **Tint Value Range** of input tint values you wish to evaluate.
    - b. Double-click in the first cell of the **Input Tints** table.
    - c. Type a Cyan input tint value, or a Red input tint value for an RGB-input DeviceLink.
    - d. <tab> to advance and enter a Magenta (or Green) input tint value.
    - e. Repeat for other input tint values.
    - f. Repeat to enter another set of input tint values.
    - g. Terminate input tint entry with <enter>.
    - h. In the **Output Tints** panel:
      - select the desired **Tint Value Range** of evaluated output tint values.
      - enter the desired **Tint Precision** of evaluated output tint values.
    - i. Click **Evaluate** below the Input Tints table.
  - To copy, paste and evaluate multiple input tints:
    - a. Select an array of input values in a spreadsheet or tab-delimited text file.
    - b. Copy.
    - c. Click in the ColorFlow Evaluate **Input Tints** table.
    - d. Select all.
    - e. Paste.
    - f. Click **Evaluate**.
  - To copy output tints for use by another application:
    - a. Click in the **Output Tints** table.
    - b. Select all.
    - c. Copy.
  - To combine the above two operations:
    - a. Select an array of input values in a spreadsheet or tab-delimited text file.
    - b. Copy.
    - c. In ColorFlow Evaluate, click **Paste - Evaluate - Copy**.
5. Click **Close**.
6. Click **Cancel**.