

_evaluate a DeviceLink

Do the following:

- To evaluate tint values through the DeviceLink:
 1. In the **Input Tints** panel, select the **Tint Value Range** of input tint values you wish to evaluate.
 2. Double-click in the first cell of the **Input Tints** table.
 3. Type a Cyan input tint value, or a Red input tint value for an RGB-input DeviceLink.
 4. <tab> to advance and enter a Magenta (or Green) input tint value.
 5. Repeat for other input tint values.
 6. Repeat to enter another set of input tint values.
 7. Terminate input tint entry with <enter>.
 8. In the **Output Tints** panel:
 - select the desired **Tint Value Range** of evaluated output tint values.
 - enter the desired **Tint Precision** of evaluated output tint values.
 9. Click **Evaluate** below the Input Tints table.
- To copy, paste and evaluate multiple input tints:
 1. Select an array of input values in a spreadsheet or tab-delimited text file.
 2. Copy.
 3. Click in the ColorFlow Evaluate **Input Tints** table.
 4. Select all.
 5. Paste.
 6. Click **Evaluate**.
- To copy output tints for use by another application:
 1. Click in the **Output Tints** table.
 2. Select all.
 3. Copy.
- To combine the above two operations:
 1. Select an array of input values in a spreadsheet or tab-delimited text file.
 2. Copy.
 3. In ColorFlow Evaluate, click **Paste - Evaluate - Copy**.