

# Creating an output process template to automatically arrange pages

You can only automatically arrange pages from the output from PDF process template. Automatically arrange pages when, for example, you want to send your files for proof and you want to save media.

1. See [Creating an output process template](#).
2. In the **Layout** section, **Size** box, select the media type that the proofing device supports.
3. In the **Max Width** box, type the maximum width of the media.
4. In the **Max Height** box, type the maximum height of the media.
5. In the **Placement** area, **Style** area, select **Auto Fit**.
6. In the **Processed File Preferences** section, select the **Send Processed Files to** option.
7. Click **Browse** to navigate to the proofing device network path or hot folder.
8. Complete the remaining process template parameters as required.
9. From the **File** menu, select **Save**.