

Editing color libraries

You can only edit User Libraries.

1. From the **Configure** menu, select **Color Definitions**.
2. In the Color Database Editor dialog box, **Color Libraries** list, select the User Library you want to edit.
3. In the **Colors** list, select the color you want to modify.
4. In the **Alternate Color** box, modify the color recipe parameters as required.
5. Click **Apply**.

The **Colors** list automatically updates the color swatch beside the color name and the modified recipe is saved.

Note: If you do not want to save the new color recipe click **Revert**. The color recipe reverts to the previously saved recipe.