

Setting the imposition software location

Use this procedure to integrate imposition software into Prinergy. For background information, see Overview of Procedures for Integrating Imposition Software.

1. From the **Tools** menu, select **Configure Imposition Applications**.
2. In the Configure Imposition Applications dialog box, click **Add**.
Note: If you are configuring Pandora on a Windows operating system, select **RunPandora.exe** (not **Pandora.exe**).
3. Locate and select the executable file for the software, and then click **Open**.
4. Click **Application Type**, and then in the list, select the software.

Tip: To delete the integrated software, in the **Application Name** area of the Configure Imposition Applications dialog box, select the software, and click **Delete**.