


Applying a calibration curve

When you select a screen instance in the DotShop window, the calibration curve that was associated with that screen instance when it was created in DotShop Composer appears in the **Calibration Curve** list in the Properties Editor.

If **Allow Plug-in to Change Calibration Curve** was selected when the screen instance was created in DotShop Composer, you can choose to apply a different calibration curve from the **Calibration Curve** list. If not, the menu is unavailable.

1. In the Acrobat window, [select the object](#) (or objects) that you want to apply screening to.
2. In the Properties Editor, in the **Screen** list, select the screen instance you want to apply.
3. In the **Calibration Curve** list, select the calibration curve you want to apply.



- If you select **%%DEFAULT%%** as the calibration curve, DotShop does not apply calibration. The calibration curve specified in the output process template will be used instead.
 - If you select **%%NONE%%** as the calibration curve, neither DotShop nor the output process template apply calibration. The "linear" value specified in the PDF file is used instead.
4. (Optional) [Adjust the colorant screen angles](#).
 5. Click **Apply**.

DotShop applies the calibration curve shown in the Properties Editor to the selected object or objects.