


Editing page geometry

You can edit the Media Box, Crop Box, Trim Box, Art Box, or Bleed Box.

1. With a PDF page displayed in Acrobat, on the Acrobat toolbar, click the **Kodak Geometry Editor** button .




Notes:

- In Adobe Acrobat 8 or 9, you can also access Kodak Geometry Editor by selecting **Advanced > Kodak Tools > Kodak Geometry Editor**.
 - In Acrobat X, select **View > Tools > Plugin Kodak Tools** and then select the **Kodak Geometry Editor** icon from the **Plugin Kodak Tools** section of the **Tools** panel on the right.
2. In the **Region** list, select the region that you want to modify, either **Media Box**, **Crop Box**, **Trim Box**, **Art Box**, or **Bleed Box**.
 3. Click **Offset** or **Coordinates**.
Note: To set the units of measurement, in Acrobat, select **Edit > Preferences > Kodak Geometry Editor**. In the Kodak Geometry Editor dialog box, in the **Units** area, select the units of measurement that you want to use, and click **OK**.
 4. To edit the Media Box, Crop Box, Trim Box, Art Box, or Bleed Box values, perform one of the following actions:
 - Enter new values for the region.
 - If **Coordinates** is selected, you can change the values in the **Top**, **Right**, **Bottom**, and **Left** boxes.

- If **Offset** is selected, you can change the values in the **Width**, **Height**, **Y Offset**, and **X Offset** boxes.

The region location on the screen moves to match the new values.

- Use the mouse to move one or more sides of the region or the entire region. The values change to match the new region location.



To move the entire trim box, position the mouse inside the trim box. Drag the box to a new location.



To move two sides of the trim box at one time, position the mouse over a corner of the trim box. Drag the sides to a new location.



To move one side of the trim box at a time, position the mouse over one side of the trim box. Drag the side to a new location.

o

5. In the **Apply To** area, select the pages to which you want to apply the new settings.
 - To apply the settings to one or more files, click **This Page**, **All Pages**, **Even Pages**, or **Odd Pages**.
 - To apply the settings to more than one file, select the **Multiple Files** check box, and click **Add File** to add new PDF files or click **Add Folder** to include all PDF files within a folder. To remove a file, select the file name in the list, and click **Remove**.

Important: Another individual should not have the PDF files open when you add them. Otherwise, an error appears.

6. Click **Apply**.

You have now modified the region measurements. However, before Prinergy and Prinergy Evo will recognize settings that were modified in the Geometry Editor, you must refine the PDF page. In Prinergy, refine using a normalize-only process template (a process template with the **ColorConvert**, **Trapping**, and **Thumbnail** check boxes cleared). In Prinergy Evo, refine using a normalize-only process template (a process template with the **Match Colors**, **Trapping**, and **Thumbnail** check boxes cleared).

See Also

[Page geometry settings](#)