

Adding a separation

1. Click the **Plate Builder Tool** button to start a Plate Builder session.
2. Perform one of the following actions:
 - On the Plate Builder toolbar, click **Edit Separations**.
 - In the Properties Editor dialog box, in the **Separation** list, select **Edit Separation List**.
3. Click **Add**.
4. In the Add Separation dialog box:
 - In the **Name** box, type a name for the separation.
 - From the **Ink Type** box, select an ink type.
 - Edit the **Color Recipe**, click the color swatch, modify values in the Color dialog box, and click **OK**.
 - Modify the **Tint Intensity** by dragging the slider or typing a value in the **Tint Intensity** box.
Entering a value of 100 fills the objects assigned to that separation with solid color.
Entering a value of less than 100 screens back the objects to the entered intensity.
 - Click **Add**.
5. In the Edit Separations dialog box, click **OK**.