

Setting colorant order

Colorant print order affects trap decisions for opaque colors especially: trap direction for opaque inks is determined only by print order, and not by neutral density. You can set and/or change the order of the list of colorants.

1. In PDF Trap Editor, select the Detailed view of the Trap Page or Trap Selection dialog box.
2. Click the **Inks** tab.
3. Select a colorant listed in the table. Click the up or down **Colorant Order** arrows to move the colorant up or down in the list.
4. Repeat step 3 for each colorant as desired.

Tip: To determine trap directions in files with many opaque colors, set the printing order using the Color Mapping dialog box in Prinergy Workshop. The color printed last defines the shape and all other colors will be pulled under it. For example, Color 1 traps to Color 2, 2 to 3, 3 to 4, and so on.