

Media Configuration settings

Edit or define a new media resource in the Media Configuration dialog box. In the **Press Runs** workspace, you can select the layout's media to view its settings in the **Properties** pane.

Nickname

The name that you specified in the Add Media dialog box

Short name

Derived from the PPD. If the PPD does not provide a short name for the device, the media nickname is displayed.

Media type

The type that you selected in the Add Media dialog box

Size

List of supported media sizes. The selected size is applied by the media resource.

Margin

Optionally set top, bottom, and side margins to add an allowance for marks that must print off the sheet.

Divided output path

The folder location that collects any divided output for this media resource

- To set or change the path, click **Select**.
- To use the default output path that is specified on the **Folders** tab in the Preferences dialog box, click **Use default**.

Note: You cannot type or copy a path into this box. Also, when printing divided output, you cannot override the folder location. It can only be changed here.

Alignment, Horizontal, Vertical

If needed, specify offset amounts to keep the image within the usable area of the media or to compensate for a small mechanical misalignment in the device. You can store different alignment information for each size that is supported by a device.

Note: This setting is effective only if the **Center Image in Media** check box is cleared on the **Output** tab in the Preferences dialog box.

Connection

Displays the Connection dialog box

Error Log

Available only if you received an error message while printing output to this device; displays the error information

Job Log

Displays a Job Log of status messages that are generated by the output device each time you print a job to that device

Punch

Displays the Punch Location dialog box

Custom Size

Displays the Edit Custom Size dialog box, from which you can access the Custom Size dialog box

PPD Information

Available only if you already edited the PPD settings using the PPD Browser; displays the PPD Information window, which lists only those settings that are no longer at their default values. To change any of these or other PPD settings, use the PPD Browser tool.