





# Control tools in Full Screen mode

For background, see [About the control toolbar](#).

	Using this tool, you can:	Comments
	Open the previous surface or the next surface.	
	Pan across the image by dragging it.	
	View a list of colorants for any spot on the image that you click.	
	Turn separations on and off.	Click <b>Apply</b> for changes to the Separations view to take effect.
	Tilt the image up relative to its original position.	If you switch to the previous or next surface after tilting the image, the new tilt will still be in effect.
	Tilt the image down relative to its original position.	
	Tilt the image right relative to its original position.	
	Tilt the image left relative to its original position.	
	Go to Window mode.	You can also press the spacebar to go to Window mode.
	Zoom in: Increase surfaces up to twice their actual size. Zoom out: Surfaces can be reduced to fit the screen.	<b>Note:</b> Color perception is affected whenever an image is greater or smaller than its actual (1" = 1") size.